

# MetraTech Metering SDK Reference Guide

Version 1.1 January 2000

The following document is provided for information purposes only. All information disclosed herein should be considered confidential and proprietary. This document is the property of MetraTech and may not be disclosed, distributed, or reproduced in part or in whole without the express written permission of MetraTech Corp.

The MetraTech logo, product, and service names are trademarks of MetraTech Corporation. All other product, services names, and registered trademarks are trademarks of respective companies.

#### Copyright © 2000 by MetraTech Corporation

This document is provided for information purposes only. All information disclosed herein should be considered confidential and proprietary. This document is the property of MetraTech and may not be disclosed, distributed, or reproduced in part or in whole without the express written permission of MetraTech.

### **MetraTech Metering SDK**

#### **Description**

The MetraTech Metering Software Development Kit.

Copyright 1998 by MetraTech Corporation All rights reserved.

THIS SOFTWARE IS PROVIDED "AS IS", AND MetraTech Corporation MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. By way of example, but not limitation, MetraTech Corporation MAKES NO REPRESENTATIONS OR WARRANTIES OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF THE LICENSED SOFTWARE OR DOCUMENTATION WILL NOT INFRINGE ANY THIRD PARTY PATENTS, COPYRIGHTS, TRADEMARKS OR OTHER RIGHTS.

Title to copyright in this software and any associated documentation shall at all times remain with MetraTech Corporation, and USER agrees to preserve the same.

### **MTMeter Class**

#### class MTMeter

The MTMeter object controls the rest of the metering library. Each application using the library should have a MTMeter object that is used to generate **MTMeterSession** objects.

#### Class Members Public:

#### MTMeter(MTMeterConfig & config)

Constructor. Init must still be called before using other methods in class.

#### virtual ~MTMeter()

Destructor. The destructor calls **Shutdown** if **Shutdown** hasn't been called already.

#### **BOOL Startup()**

Initialize the object. This function must be called before any other method is used in this class.

#### **BOOL Shutdown()**

Shuts down the class. This function frees up any memory used.

#### MTMeterSession \* CreateSession(const char \* serviceName)

Generates a new **MTMeterSession** to hold property values that are used to describe a metered event.

#### unsigned long GetLastError() const

Return the error code, or 0 if there was no error.

#### **MTMeterError** \* **GetLastErrorObject()** const

Returns an **MTMeterError** object that holds information about the last error. The MTMeterError object must be deleted after it is used.

# static void EnableDiagnosticLogging(MTDebugLogLevel level, FILE \* logStream)

Call this function if you're having problems debugging an application using the metering object. The log produced can help track down bugs and can help MetraTech diagnose problems. This method only enables logging in the debug version of the library. In the release version, it does nothing.

#### **Protected:**

#### NetMeterAPI \* mpAPI

Object used by the implementation of MTMeter

#### Private:

#### ErrorObject \* mpErrObj

Object used by the implementation of MTMeter

# void SetError(unsigned long aCode, const char \* apModule, int aLine, const char \* apProcedure)

method used by the implementation of MTMeter

#### void SetError(const ErrorObject \* apError)

method used by the implementation of MTMeter

### **MTMeter::CreateSession**

MTMeterSession \* MTMeter::CreateSession(const char \* serviceName)

Generates a new **MTMeterSession** to hold property values that are used to describe a metered event.

#### **Return Value** Session that will hold properties. Must be deleted when no longer needed.

**Parameters** *serviceName* 

Name of service. Must match the name of a service defined on the metering server.

### MTMeter::EnableDiagnosticLogging

static void MTMeter::EnableDiagnosticLogging(MTDebugLogLevel level, FILE \* logStream)

Call this function if you're having problems debugging an application using the metering object. The log produced can help track down bugs and can help MetraTech diagnose problems. This method only enables logging in the debug version of the library. In the release version, it does nothing.

**Parameters** 

level

Detail level used to log messages. See MTDebugLogLevel for values.

logStream

stdio file pointer where logging messages are sent.

### MTMeter::GetLastError

unsigned long MTMeter::GetLastError(void)

Return the error code, or 0 if there was no error.

**Return Value** 

Error code. For Windows NT, the code is either a Win32 error or it's an error code defined in sdk\_msg.h.

## MTMeter::GetLastErrorObject

MTMeterError \* MTMeter::GetLastErrorObject(void)

Returns an **MTMeterError** object that holds information about the last error. The MTMeterError object must be deleted after it is used.

**Return Value** 

MTMeteringError object representing the last error that occurred in the MTMeter object or NULL if there was no error. The object must be deleted after use.

### MTMeter::MTMeter

**MTMeter::MTMeter(MTMeterConfig &** *config***)** 

Constructor. Init must still be called before using other methods in class.

Parameters config

Configuration object which holds specifics about the transport and protocol

used to send messages to the server.

See Also MTMeterConfig

### MTMeter::Shutdown

**BOOL MTMeter::Shutdown(void)** 

Shuts down the class. This function frees up any memory used.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

### MTMeter::Startup

**BOOL MTMeter::Startup(void)** 

Initialize the object. This function must be called before any other method is used

in this class.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

**MTMeter::~MTMeter** 

virtual MTMeter::~MTMeter(void)

Destructor. The destructor calls **Shutdown** if **Shutdown** hasn't been called already.

## **MTMeterConfig Class**

#### class MTMeterConfig

The MTMeterConfig object holds configuration information about the transport and protocol used by the SDK.

#### Class Members Public:

#### virtual ~MTMeterConfig()

Destructor.

#### enum Protocol

Protocol choices used to send sessions. Currently MSIX is the only protocol supported.

#### **Protected:**

#### virtual NetMeterAPI \* GetAPI()

Used by MTMeter only. Do not use this function in any other case.

### MTMeterConfig::~MTMeterConfig

virtual MTMeterConfig::~MTMeterConfig(void)

Destructor.

### **MTMeterError Class**

#### class MTMeterError

The MeteringError object holds an error code and allows you to generate an error message for each code. The MeteringError object also holds the time an error occurred and information of interest to the developer.

#### **Class Members**

#### virtual ~MTMeterError()

Destructor.

#### virtual unsigned long GetErrorCode() const

Return the error code.

#### virtual BOOL GetErrorMessage(wchar\_t \* buffer, int & bufferSize) const

Get the error message in Unicode. GetErrorMessage fills the buffer as far as possible and terminates it with a null character. If the buffer size is zero, GetErrorMessage returns the number of wchar\_t values to hold the message and a terminating null character.

#### virtual BOOL GetErrorMessage(char \* buffer, int & bufferSize) const

Get the error message in ASCII. GetErrorMessage fills the buffer as far as possible and terminates it with a null character. If the buffer size is zero, GetErrorMessage returns the number of char values to hold the message and a terminating null character.

#### virtual int GetErrorMessageEx(char \* buffer, int & bufferSize) const

Returns information to the programmer that can be useful in diagnosing the source of an error. GetErrorMessageEx fills the buffer as far as possible and terminates it with a null character. If the buffer size is zero, GetErrorMessage returns the number of char values to hold the message and a terminating null character.

#### virtual time t GetErrorTime() const

Returns the time the error occurred.

#### MTMeterError()

Constructor. The constructor object is protected because MTMeterError objects cannot be created directly.

### MTMeterError::GetErrorCode

virtual unsigned long MTMeterError::GetErrorCode(void)

Return the error code.

**Return Value** 

Error code. For Windows NT, the code is either a Win32 error or it's an error code defined in sdk\_msg.h.

### MTMeterError::GetErrorMessage

 $\label{eq:continuous_continuous$ 

bufferSize)

Get the error message in Unicode. GetErrorMessage fills the buffer as far as possible and terminates it with a null character. If the buffer size is zero,

 $GetErrorMessage\ returns\ the\ number\ of\ wchar\_t\ values\ to\ hold\ the\ message\ and\ a$ 

terminating null character.

**Return Value** FALSE if the buffer is NULL, otherwise TRUE.

Parameters *buffer* 

Pointer to buffer of type wchar\_t that will hold the error message.

bufferSize

Size of buffer (number of wchar\_t values it can hold). If zero, it will be set to the size of the buffer required to hold the string and the terminating zero.

## MTMeterError::GetErrorMessage

virtual BOOL MTMeterError:: GetErrorMessage (char \* buffer, int &

bufferSize)

Get the error message in ASCII. GetErrorMessage fills the buffer as far as possible and terminates it with a null character. If the buffer size is zero, GetErrorMessage returns the number of char values to hold the message and a

terminating null character.

**Return Value** FALSE if the buffer is NULL, otherwise TRUE.

Parameters buffer

Pointer to buffer of type char that will hold the error message.

buffer Size

Size of buffer (number of char values it can hold). If zero, it will be set to the size of the buffer required to hold the string and the terminating zero.

## MTMeterError::GetErrorMessageEx

virtual int MTMeterError::GetErrorMessageEx(char \* buffer, int &

bufferSize)

Returns information to the programmer that can be useful in diagnosing the source of an error. GetErrorMessageEx fills the buffer as far as possible and terminates it with a null character. If the buffer size is zero, GetErrorMessage returns the number of char values to hold the message and a terminating null character.

**Return Value** FALSE if the buffer is NULL, otherwise TRUE.

Parameters buffer

Pointer to buffer of type char that will hold the message.

bufferSize

Size of buffer (number of char values it can hold). If zero, it will be set to the size of the buffer required to hold the string and the terminating zero.

### MTMeterError::GetErrorTime

virtual time\_t MTMeterError::GetErrorTime(void)

Returns the time the error occurred.

**Return Value** time\_t value holding the time the error occurred, in GMT.

### MTMeterError::MTMeterError

MTMeterError::MTMeterError(void)

Constructor. The constructor object is protected because MTMeterError objects cannot be created directly.

### MTMeterError::~MTMeterError

virtual MTMeterError::~MTMeterError(void)

Destructor.

### **MTMeterHTTPConfig Class**

#### class MTMeterHTTPConfig

The MTMeterConfig object holds configuration information about the HTTP transport and protocol used by the SDK.

# MTMeterHTTPConfig(const char \* proxyName = NULL, Protocol prot = MSIX\_PROTOCOL)

Constructor. You must still call Init to initialize the Metering SDK.

#### virtual ~MTMeterHTTPConfig()

Destructor. The destructor calls close if the Metering SDK hasn't been closed already.

# void AddServer(int priority, const char \* serverName, int port, BOOL secure, const char \* username, const char \* password)

Add a Metering Server to be used to meter sessions. More than one server may be added. The library will attempt to send sessions to the server with the highest priority first, then attempt to send to servers with lower priority if the attempt fails. The higher the priority argument value, the higher the priority of the server. If more than one server has the same same priority, the library will pick any one of these at random.

#### void SetConnectTimeout(int timeout)

Set the duration in milliseconds that each operation will wait before timing out. If a network operation takes longer than this timeout, the Metering SDK will try again until all its retries have been used. If the SDK is still unable to send the message to the server, the message will be sent to the next server added with **AddServer**. If the message fails to be sent to any server, the operation will return an error.

#### int GetConnectTimeout() const

Retrieves the timeout value in milliseconds.

#### void SetConnectRetries(int retries)

Sets the number of retries to make before giving up. If a network operation fails more times than this for any reason, the Metering SDK will attempt to resend the message to the next server listed with **AddServer**.

#### int GetConnectRetries() const

Get the number of retries each network operation will make before moving to the next server.

#### **Class Members** Protected:

#### virtual NetMeterAPI \* GetAPI()

Called by MTMeter. Do not use this function in other cases.

#### **Protected:**

#### MSIXNetMeterAPI \* mpAPI

Object used by the implementation of MTMeterHTTPConfig.

## MTMeterHTTPConfig::AddServer

**void MTMeterHTTPConfig::AddServer(int** *priority*, **const char** \* *serverName*, **int** *port*, **BOOL** *secure*, **const char** \* *username*, **const char** \* *password*)

Add a Metering Server to be used to meter sessions. More than one server may be added. The library will attempt to send sessions to the server with the highest priority first, then attempt to send to servers with lower priority if the attempt fails. The higher the priority argument value, the higher the priority of the server. If more than one server has the same same priority, the library will pick any one of these at random.

#### **Parameters**

priority

Priority of the server. The server with the highest value as this argument will be used first.

serverName

Hostname of the server.

port

Port number on the server. Usually port 80 when not using SSL and 443 when using SSL. A value from the PortNumbers enumeration can be used for this argument.

secure

If TRUE, use SSL to encrypt all communications. If FALSE, don't use encryption when sending data.

username

Username used for HTTP authentication on the server.

password

Password used for HTTP authentication on the server.

### **MTMeterHTTPConfig::GetConnectRetries**

int MTMeterHTTPConfig::GetConnectRetries(void)

Get the number of retries each network operation will make before moving to the

next server.

**Return Value** Number of retries to attempt

### MTMeterHTTPConfig::GetConnectTimeout

int MTMeterHTTPConfig::GetConnectTimeout(void)

Retrieves the timeout value in milliseconds.

**Return Value** Timeout value in milliseconds.

## MTMeterHTTPConfig::MTMeterHTTPConfig

MTMeterHTTPConfig::MTMeterHTTPConfig(const char \* proxyName = NULL, Protocol prot = MSIX\_PROTOCOL)

Constructor. You must still call Init to initialize the Metering SDK.

Parameters NULL

An optional proxy server setting. If the proxy server's name is "proxy1" and runs on port 8000, the syntax of this parameter would be "http:://proxy1:8000". If the parameter is NULL, no proxy server will be used.

MSIX PROTOCOL

Protocol to use when sending messages to the server. Currently only the Metered Session Information Exchange (MSIX) protocol is supported.

### **MTMeterHTTPConfig::SetConnectRetries**

void MTMeterHTTPConfig::SetConnectRetries(int retries)

Sets the number of retries to make before giving up. If a network operation fails more times than this for any reason, the Metering SDK will attempt to resend the message to the next server listed with **AddServer**.

Parameters

retries

Number of retries to attempt before trying the next host.

### MTMeterHTTPConfig::SetConnectTimeout

void MTMeterHTTPConfig::SetConnectTimeout(int timeout)

Set the duration in milliseconds that each operation will wait before timing out. If a network operation takes longer than this timeout, the Metering SDK will try again until all its retries have been used. If the SDK is still unable to send the message to the server, the message will be sent to the next server added with **AddServer**. If the message fails to be sent to any server, the operation will return an error.

**Parameters** 

timeout

Timeout value in milliseconds.

## MTMeterHTTPConfig::~MTMeterHTTPConfig

virtual MTMeterHTTPConfig::~MTMeterHTTPConfig(void)

Destructor. The destructor calls close if the Metering SDK hasn't been closed already.

### **MTMeterSession Class**

class MTMeterSession

The MTMeterSession object holds the property values for a metered session. Objects of this type are created by MTMeter::CreateSession. InitProperty should be called for each property value before Save or Close is called to send the properties to the server. SetProperty may be called to modify properties before the session is Closed, and GetProperty can be used to retrieve property values from the session.

#### **Class Members**

#### MTMeterSession()

Constructor. You cannot construct MTMeterSession objects directly.

#### virtual ~MTMeterSession()

Destructor. For the properties of the session to be sent to the metering server, **Close** or **Save** must be called before deleting the object.

#### virtual BOOL Close()

After each property has been initialized to the correct value, Close sends the session and its parents and children, when appropriate, to the metering server. The session is marked complete by a call to Close and further modification is not allowed on the session object. The metering server is allowed to begin processing a session after it has been closed. When a session is closed, any parents of the session are saved but will still be modifiable. Any children of the session will be closed and will not allow further modification.

#### virtual BOOL Save()

After each property has been initialized to appropriate values, Save sends the session and its parents and children when appropriate to the metering server. After a session has been saved, it is still possible to modify property values by calling **SetProperty**. A session can be saved any number of times before finally being closed. If a session could potentially remain open for a long period of time, saving the session periodically will ensure that the properties are sent to the server. When a session is saved, any parents and children of the session will be saved and will still allow further modification.

#### virtual void GetSessionID(char \* sessionId) const

Get a session identifier that uniquely identifies a session on the Metering Server.

#### virtual void GetReferenceID(char \* referenceId) const

Get a reference ID that can be displayed to a user. This ID is shorter and more easily displayed and read by the user. The reference ID samples part of the session ID. Therefore it doesn't uniquely identify a session. There is a small probability that a user will have two sessions with the same reference ID. Other information about the session can then be used to determine which session a user is referring to.

#### virtual unsigned long GetLastError() const

Return the error code, or 0 if there was no error.

#### virtual MTMeterError \* GetLastErrorObject() const

Return an **MTMeterError** object that holds information about the last error. The **MTMeterError** object must be deleted after it is used.

#### virtual BOOL InitProperty(const char \* name, const wchar\_t \* val)

Initialize and initially set a property's Unicode value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### virtual BOOL InitProperty(const char \* name, const char \* val)

Initialize and initially set a property's ASCII value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### virtual BOOL InitProperty(const char \* name, int val)

Initialize and initially set a property's integer value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### virtual BOOL InitProperty(const char \* name, float val)

Initialize and initially set a property's float value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### virtual BOOL InitProperty(const char \* name, double val)

Initialize and initially set a property's double value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### virtual BOOL InitProperty(const char \* name, time t timestamp)

Initialize and initially set a property's timestamp value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### virtual BOOL SetProperty(const char \* name, const wchar\_t \* val)

Modify a session's Unicode string value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

#### virtual BOOL SetProperty(const char \* name, const char \* val)

Modify a session's ASCII string value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

#### virtual BOOL SetProperty(const char \* name, int val)

Modify a session's integer value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

#### virtual BOOL SetProperty(const char \* name, float val)

Modify a session's float value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

#### virtual BOOL SetProperty(const char \* name, double val)

Modify a session's double value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

#### virtual BOOL SetProperty(const char \* name, time\_t val)

Modify a session's timestamp value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

#### virtual BOOL GetProperty(const char \* name, const wchar\_t \* \* val)

Retrieve a session's Unicode string value. The property must have been initialized before GetProperty can return it.

#### virtual BOOL GetProperty(const char \* name, const char \* val)

Retrieve a session's ASCII string value. The property must have been initialized before GetProperty can return it.

#### virtual BOOL GetProperty(const char \* name, int & val)

Retrieve a session's integer value. The property must have been initialized before GetProperty can return it.

#### virtual BOOL GetProperty(const char \* name, float & val)

Retrieve a session's float value. The property must have been initialized before GetProperty can return it.

#### virtual BOOL GetProperty(const char \* name, double & val)

Retrieve a session's double value. The property must have been initialized before GetProperty can return it.

#### virtual BOOL GetProperty(const char \* name, time t & timestamp)

Retrieve a session's time value, in GMT. The property must have been initialized before GetProperty can return it.

#### virtual MTMeterSession \* CreateChildSession(const char \* serviceName)

Create a child of this session. Any number of children can be created for a parent session. Once **Close** has been called on a session, no more children can be created. Sessions that have been saved can still have more children added to them. When the child is deleted, it is removed from the parent. When a parent session is deleted, it deletes any children still connected to it.

### MTMeterSession::Close

#### virtual BOOL MTMeterSession::Close(void)

After each property has been initialized to the correct value, Close sends the session and its parents and children, when appropriate, to the metering server. The session is marked complete by a call to Close and further modification is not

allowed on the session object. The metering server is allowed to begin processing a session after it has been closed. When a session is closed, any parents of the session are saved but will still be modifiable. Any children of the session will be closed and will not allow further modification.

**Return Value** 

If TRUE, the function succeeded. If FALSE, the function failed and **GetLastErrorObject** can be called to get more information.

### MTMeterSession::CreateChildSession

virtual MTMeterSession \* MTMeterSession::CreateChildSession(const char \* serviceName)

Create a child of this session. Any number of children can be created for a parent session. Once **Close** has been called on a session, no more children can be created. Sessions that have been saved can still have more children added to them. When the child is deleted, it is removed from the parent. When a parent session is deleted, it deletes any children still connected to it.

**Return Value** 

Child MTMeterSession. Either the child must be deleted, or its parent must be deleted. If CreateChildSession returns NULL, **GetLastErrorObject** can be called to get more information.

**Parameters** 

serviceName

Service name of child session.

### MTMeterSession::GetLastError

virtual unsigned long MTMeterSession::GetLastError(void)

Return the error code, or 0 if there was no error.

**Return Value** 

Error code. For Windows NT, the code is either a Win32 error or it's an error code defined in sdk\_msg.h.

## MTMeterSession::GetLastErrorObject

virtual MTMeterError \* MTMeterSession::GetLastErrorObject(void)

Return an MTMeterError object that holds information about the last error. The

MTMeterError object must be deleted after it is used.

**Return Value** MTMeterError object representing the last error that occurred in the

MTMeterSession object or NULL if there was no error. The object must be

deleted after use.

### MTMeterSession::GetProperty

 ${\bf virtual\ BOOL\ MTMeter Session:: Get Property (const\ char\ * name,\ double\ \& }$ 

val)

Retrieve a session's double value. The property must have been initialized before

GetProperty can return it.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

**Parameters** name

Property name. The name must match the property name in the service

definition.

val

A reference to a double that will hold the property value.

### MTMeterSession::GetProperty

virtual BOOL MTMeterSession::GetProperty(const char \* name, int & val)

Retrieve a session's integer value. The property must have been initialized before

GetProperty can return it.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters

name

Property name. The name must match the property name in the service definition.

val

A reference to an integer that will hold the property value.

### MTMeterSession::GetProperty

virtual BOOL MTMeterSession::GetProperty(const char \* name, float & val)

Retrieve a session's float value. The property must have been initialized before

GetProperty can return it.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

Parameters nan

Property name. The name must match the property name in the service

definition.

val

A reference to a float that will hold the property value.

## MTMeterSession::GetProperty

virtual BOOL MTMeterSession::GetProperty(const char \* name, const wchar\_t \* \* val)

Retrieve a session's Unicode string value. The property must have been initialized

before GetProperty can return it.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters name

Property name. The name must match the property name in the service

definition.

val

Pointer to a wchar\_t pointer that will point to the Unicode string value. The

value is constant and must not be modified.

## MTMeterSession::GetProperty

virtual BOOL MTMeterSession::GetProperty(const char \* name, time\_t &

timestamp)

Retrieve a session's time value, in GMT. The property must have been initialized

before GetProperty can return it.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

**Parameters** name

Property name. The name must match the property name in the service

definition.

timestamp

A reference to a time\_t that will hold the property value, in GMT.

## MTMeterSession::GetProperty

virtual BOOL MTMeterSession::GetProperty(const char \* name, const char

\* \* val)

Retrieve a session's ASCII string value. The property must have been initialized

before GetProperty can return it.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

**Parameters** name

Property name. The name must match the property name in the service

definition.

val

Pointer to a char pointer that will point to the ASCII string value. The value is

constant and must not be modified.

### MTMeterSession::GetReferenceID

virtual void MTMeterSession::GetReferenceID(char \* referenceId)

Get a reference ID that can be displayed to a user. This ID is shorter and more easily displayed and read by the user. The reference ID samples part of the session ID. Therefore it doesn't uniquely identify a session. There is a small probability that a user will have two sessions with the same reference ID. Other information about the session can then be used to determine which session a user is referring to.

#### **Parameters**

referenceId

Pointer to a character buffer at least 10 bytes long. This will hold the reference ID and a null terminating byte. The reference ID is a nine character string made up of uppercase characters and numbers. The size of this buffer is not checked.

### MTMeterSession::GetSessionID

virtual void MTMeterSession::GetSessionID(char \* sessionId)

Get a session identifier that uniquely identifies a session on the Metering Server.

#### **Parameters**

sessionId

Pointer to a character buffer at least 23 bytes long. This will hold the session ID and a null terminating byte. The size of this buffer is not checked.

## MTMeterSession::InitProperty

virtual BOOL MTMeterSession::InitProperty(const char \* name, const char \* val)

Initialize and initially set a property's ASCII value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

#### **Return Value**

If TRUE, the function succeeded. If FALSE, the function failed and **GetLastErrorObject** can be called to get more information.

**Parameters** 

name

Property name. The name must match the property name in the service definition.

val

Pointer to an ASCII string that holds the property's value. The property must be specified as an ASCII string in the service definition.

## MTMeterSession::InitProperty

virtual BOOL MTMeterSession::InitProperty(const char \* name, double val)

Initialize and initially set a property's double value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

**Return Value** 

If TRUE, the function succeeded. If FALSE, the function failed and **GetLastErrorObject** can be called to get more information.

**Parameters** 

name

Property name. The name must match the property name in the service definition.

val

The property's double value. The property must be specified as a double in the service definition.

## MTMeterSession::InitProperty

virtual BOOL MTMeterSession::InitProperty(const char \* name, time\_t

timestamp)

Initialize and initially set a property's timestamp value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

**Return Value** 

If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters nam

Property name. The name must match the property name in the service

definition.

timestamp

The property's time value, in GMT. The property must be specified as a timestamp in the service definition.

### MTMeterSession::InitProperty

virtual BOOL MTMeterSession::InitProperty(const char \* name, int val)

Initialize and initially set a property's integer value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or

Close has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

Parameters name

Property name. The name must match the property name in the service

definition.

val

The property's integer value. The property must be specified as an integer in the service definition.

### MTMeterSession::InitProperty

virtual BOOL MTMeterSession::InitProperty(const char \* name, float val)

Initialize and initially set a property's float value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters name

Property name. The name must match the property name in the service definition.

val

The property's float value. The property must be specified as a float in the service definition.

### MTMeterSession::InitProperty

 ${\bf virtual\ BOOL\ MTMeter Session:: Init Property (const\ char\ * name,\ const}$ 

wchar\_t \* val)

Initialize and initially set a property's Unicode value. InitProperty must be called before **SetProperty** may be called. InitProperty may not be called after **Save** or

Close has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

**Parameters** name

Property name. The name must match the property name in the service

definition.

val

Pointer to a Unicode string that holds the property's value. The property must

be specified as a Unicode string in the service definition.

### MTMeterSession::MTMeterSession

MTMeterSession::MTMeterSession(void)

Constructor. You cannot construct MTMeterSession objects directly.

### MTMeterSession::Save

virtual BOOL MTMeterSession::Save(void)

After each property has been initialized to appropriate values, Save sends the session and its parents and children when appropriate to the metering server. After a session has been saved, it is still possible to modify property values by calling **SetProperty**. A session can be saved any number of times before finally being closed. If a session could potentially remain open for a long period of time, saving the session periodically will ensure that the properties are sent to the server. When a session is saved, any parents and children of the session will be saved and will still allow further modification.

#### **Return Value**

If TRUE, the function succeeded. If FALSE, the function failed and **GetLastErrorObject** can be called to get more information.

### MTMeterSession::SetProperty

virtual BOOL MTMeterSession::SetProperty(const char \* name, int val)

Modify a session's integer value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

**Parameters** name

Property name. The name must match the property name in the service

definition.

val

The property's integer value. The property must be specified as an integer in the service definition.

## MTMeterSession::SetProperty

**virtual BOOL MTMeterSession::SetProperty(const char** \* name, **const char** \* val)

Modify a session's ASCII string value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

Parameters name

Property name. The name must match the property name in the service definition.

val

The property's ASCII string value. The property must be specified as an ASCII string in the service definition.

## MTMeterSession::SetProperty

virtual BOOL MTMeterSession::SetProperty(const char \* name, time\_t val)

Modify a session's timestamp value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters name

Property name. The name must match the property name in the service

definition.

val

The property's time value, in GMT. The property must be specified as a timestamp in the service definition.

## MTMeterSession::SetProperty

virtual BOOL MTMeterSession::SetProperty(const char \* name, float val)

Modify a session's float value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

GetLastErrorObject can be called to get more information.

Parameters name

Property name. The name must match the property name in the service

definition.

val

The property's float value. The property must be specified as a float in the service definition.

## MTMeterSession::SetProperty

virtual BOOL MTMeterSession::SetProperty(const char \* name, double val)

Modify a session's double value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters name

Property name. The name must match the property name in the service definition.

val

The property's double value. The property must be specified as a double in the service definition.

### MTMeterSession::SetProperty

virtual BOOL MTMeterSession::SetProperty(const char \* name, const wchar\_t \* val)

Modify a session's Unicode string value. **InitProperty** must be called before SetProperty may be called. SetProperty may not be called after **Close** has been called.

**Return Value** If TRUE, the function succeeded. If FALSE, the function failed and

**GetLastErrorObject** can be called to get more information.

Parameters name

Property name. The name must match the property name in the service definition.

val

The property's Unicode string value. The property must be specified as a Unicode string in the service definition.

### MTMeterSession::~MTMeterSession

virtual MTMeterSession::~MTMeterSession(void)

Destructor. For the properties of the session to be sent to the metering server, **Close** or **Save** must be called before deleting the object.

## MTDebugLogLevel

```
enum MTDebugLogLevel {
    MT_LOG_NONE,
    MT_LOG_INFO,
    MT_LOG_DEBUG
};
```

Values that can be passed into MTMeter::EnableLogging

#### **Members**

#### MT\_LOG\_NONE

Do not display any logging information.

#### MT\_LOG\_INFO

Only display informational messages.

#### MT LOG DEBUG

Display informational messages and diagnostic/debugging messages.

# MTMeterConfig::Protocol

```
enum MTMeterConfig {
     MSIX_PROTOCOL
};
```

Protocol choices used to send sessions. Currently MSIX is the only protocol supported.

#### **Members**

#### MSIX\_PROTOCOL

Metered Session Information Exchange protocol. See www.msix.org for more details.